









ANALOG_IN v1.0

Available Languages

Relay Ladder



Function Block



Structured Text

ANALOG_IN(Raw_Max, Raw_Min, EU_Max, EU_Min, Sensor, EU_Value);

Parameters

Required	Name	Data Type	Usage	Description
X	ANALOG_IN	ANALOG_IN	InOut	
	EnableIn	BOOL	Input	
	EnableOut	BOOL	Output	
X	Raw_Max	REAL	Input	Maximum Bit Value
X	Raw_Min	REAL	Input	Minimum Bit Value
X	EU_Max	REAL	Input	Engineering Unit Maximum
X	EU_Min	REAL	Input	Analog Channel, Source
X	Sensor	REAL	Input	Analog Channel, Source
X	EU_Value	REAL	Output	Scaled Engineering Unit Value

Extended Description

Execution

Condition	Description
EnableIn is true	

Name	Default	Data Type	Scope
Raw_Max Maximum Bit Value Usage: Required: Visible: External Access: OPC UA Access: <i>Raw_Max - ANALOG_IN/Logic - #2</i>	0.0 Input Parameter Yes Yes Read/Write None	REAL	ANALOG_IN
Raw_Min Minimum Bit Value Usage: Required: Visible: External Access: OPC UA Access: <i>Raw_Min - ANALOG_IN/Logic - #3</i>	0.0 Input Parameter Yes Yes Read/Write None	REAL	ANALOG_IN
EU_Max Engineering Unit Maximum Usage: Required: Visible: External Access: OPC UA Access: <i>EU_Max - ANALOG_IN/Logic - #4</i>	0.0 Input Parameter Yes Yes Read/Write None	REAL	ANALOG_IN
EU_Min Analog Channel, Source Usage: Required: Visible: External Access: OPC UA Access: <i>EU_Min - ANALOG_IN/Logic - #5</i>	0.0 Input Parameter Yes Yes Read/Write None	REAL	ANALOG_IN
Sensor Analog Channel, Source Usage: Required: Visible: External Access: OPC UA Access: <i>Sensor - ANALOG_IN/Logic - #1</i>	0.0 Input Parameter Yes Yes Read/Write None	REAL	ANALOG_IN
EU_Value Scaled Engineering Unit Value Usage: Required: Visible: External Access: OPC UA Access: <i>EU_Value - ANALOG_IN/Logic - *#7</i>	0.0 Output Parameter Yes Yes Read Only None	REAL	ANALOG_IN

Name	Default	Data Type	Scope
Analog Data Type for Add on Instruction Usage: External Access: OPC UA Access: <i>Analog - ANALOG_IN/Logic - *#6</i>	 Local Tag None None	SCALE	ANALOG_IN
Analog.EnableIn Data Type for Add on Instruction	1	BOOL	
Analog.In Data Type for Add on Instruction <i>Analog.In - ANALOG_IN/Logic - *#1</i>	0.0	REAL	
Analog.InRawMax Data Type for Add on Instruction <i>Analog.InRawMax - ANALOG_IN/Logic - *#2</i>	0.0	REAL	
Analog.InRawMin Data Type for Add on Instruction <i>Analog.InRawMin - ANALOG_IN/Logic - *#3</i>	0.0	REAL	
Analog.InEUMax Data Type for Add on Instruction <i>Analog.InEUMax - ANALOG_IN/Logic - *#4</i>	0.0	REAL	
Analog.InEUMin Data Type for Add on Instruction <i>Analog.InEUMin - ANALOG_IN/Logic - *#5</i>	0.0	REAL	
Analog.Limiting Data Type for Add on Instruction	0	BOOL	
Analog.EnableOut Data Type for Add on Instruction	0	BOOL	
Analog.Out Data Type for Add on Instruction <i>Analog.Out - ANALOG_IN/Logic - #7</i>	0.0	REAL	
Analog.MaxAlarm Data Type for Add on Instruction	0	BOOL	
Analog.MinAlarm Data Type for Add on Instruction	0	BOOL	
Analog.Status Data Type for Add on Instruction	16#0000_0000	DINT	
Analog.InstructFault Data Type for Add on Instruction	0	BOOL	
Analog.InRawRangeInv Data Type for Add on Instruction	0	BOOL	

```
1 Analog.In := Sensor;  
2 Analog.InRawMax := Raw_Max;  
3 Analog.InRawMin := Raw_Min;  
4 Analog.InEUMax := EU_Max;  
5 Analog.InEUMin := EU_Min;  
6 SCL(Analog);  
7 EU_Value := Analog.Out;
```

DISPENSE**MainTask****MainProgram****MainRoutine**

Ladder Diagram1

Add-On Instructions

Instruction Definition3

ANALOG_IN

Parameter Listing5

Local Tag Listing6

Logic Routine7